

Windows 10 2019 13m OS Image Release Notes



Overview

This checklist will help you prepare for the installation of the Windows 10 13m OS image.

General Information	
○ Release Date	12-Jan-2022
○ Files included	os_win10_x64_010622_112553_os1.iso os_win10_x64_010622_112553_os2.iso
○ File size	os_win10_x64_010622_112553_os1.iso: 4425750528 os_win10_x64_010622_112553_os2.iso: 4185802752
○ Checksum	Fiery checksum: os_win10_x64_010622_112553_os1.iso: 1601125357 os_win10_x64_010622_112553_os2.iso: 1186609053 MD5 checksum: os_win10_x64_010622_112553_os1.iso: a79dac69d690684b0a9561a56ce46fc os_win10_x64_010622_112553_os2.iso: 598630bf2644bb67fe7e0609eaeaa5b

The Windows 10 13m OS image includes the following updates:

SI.No	Security updates/ Patches
1	2021-09 Cumulative Update Preview for Windows 10 Version 1809 for x64-based Systems (KB5005625)
2	2021-09 Cumulative Update Preview for .NET Framework 3.5, 4.7.2 and 4.8 for Windows 10 Version 1809 for x64 (KB5005653)
3	2021-01 Update for Windows 10 Version 1809 for x64-based Systems (KB4589208)
4	Security Update for Windows 10 Version 1809 for x64-based Systems (KB4535680)
5	2021-09 Cumulative Update for Windows 10 Version 1809 for x64-based Systems (KB5005568)
6	Update for Microsoft Defender Antivirus antimalware platform - KB4052623 (Version 4.18.2109.6)
7	Security Intelligence Update for Microsoft Defender Antivirus - KB2267602 (Version 1.349.2068.0)
8	Windows Malicious Software Removal Tool x64 - v5.93 (KB890830)

Windows 10 2019 13m OS Image Release Notes



1. Known issues:
 - None
2. OS versions:
 - win1064.6.2.1.13m
3. Driver Changes:
 - None.

Important

This OS image includes a Microsoft Windows update **that impacts Point and Print (PNP) workflows for non-administrator users on Windows 10 and Windows 11** client machines. For more information read Microsoft's bulletin by visiting the link below:

<https://support.microsoft.com/en-us/topic/kb5005010-restricting-installation-of-new-printer-drivers-after-applying-the-july-6-2021-updates-31b91c02-05bc-4ada-a7ea-183b129578a7>

Installation of the Windows 10 13m OS image

- 1) Go to <http://www.efi.com> download center
- 2) Select *OS Image Downloads*
- 3) Choose your printer's brand and model
- 4) Select *Windows 10 IoT Enterprise 2019 LTSC*
- 5) Read the instructions and check the box to confirm you read, understood, and agree to the Microsoft Software License Terms and EFI's general Terms of Use and Privacy Policy.
- 6) Select *Accept* and carefully read the instructions before downloading the two image files
 - System_Software_2_Win10_13m.iso (os_win10_x64_010622_112553_os1.iso)
 - System_Software_3_Win10_13m.iso (os_win10_x64_010622_112553_os2.iso)
- 7) The server software [DVD1] and the User Software [DVD4] remain the same
- 8) The OS Software and release note was scanned with antivirus software and believed to be virus free.